

Set up your keyboard's key positions by adjusting the motor angles:



I recommend using the rotary encoder



for more precise positioning of the clicker.

Each click on the rotary encoder switches the active motor, preparing it for either clockwise or counterclockwise rotation.

Sample on YouTube https://youtu.be/NIAYTM6Bs1w

When the clicker is near the desired key:

Set "Key Name"

Press "Get actual data"

Key Name: K						
Get actual data	FI (First Motor) angle:	50 SE	E (Second Motor)	angle:	45]
TH (Third Motor)	angle: 34 💲 FO (Fou	rth Motor) a	angle: 10	Check k	Сеу	Add Key


Press "Check Key".

If the key on the keyboard was successfully clicked, press "Add key" and "Save".



You can verify individual key clicks by selecting the "Use it" and "Click" checkboxes next to the keys you want to test. Set the number of repetitions to evaluate the consistency of the key clicks. Then, press the "Check Uselt Keys" button.


Save




Ensure you confirm every change by pressing the "Save" button.

Check keys

This feature enables you to press the added keys in the desired sequence




Scripts



This feature lets you set up scripted combinations. The 'Command Key' is a phrase in English that you can vocalize using the 'Listen Mic' function.

Listen mic



By combining the 'Scripts' and 'Listen Mic' features, saying 'Repeat Hello' will result in typing 'hello' five times."

Script h(2)e(3)l(3)l(3)o(2)(R5) mean:

Press h and wait 2 seconds

Press e and wait 3 seconds

Press I and wait 3 seconds

Press I and wait 3 seconds

Press o and wait 2 seconds

Repeat 5 times

Just click "Listen command" and say "Command Key" phrase

Listen

Stop Listening

Click on 'Stop Listening' when you wish to deactivate this feature. If needed, you can manually edit the 'scripts.json' file in the Data folder, as the application currently lacks a 'Delete Script' function.